

Changing Windows Agent Configuration

The Windows Agent installer automatically sets default parameters for the configuration. If you want to change the default configuration values, you can do so by using your [Windows CDP Agent Configuration Utility](#).


Note

In Standard and Advanced Editions, both CDP Agent and CDP Server are built-in and do not need to be installed separately. To configure CDP Agent and CDP Server, use [Windows CDP Configuration Utility](#). See more in [Accessing CDP Configuration Utility](#) and [Configuring CDP Agent Port](#).

Agent Configuration Options

By default, the agent config file is located in

C:\Program Files\R1Soft CDP Agent\conf



```

#####
#
# Copyright (c) 2009 by R1Soft All rights reserved
#
#####
# configuration directory path
ConfDir=..\conf

# local address agent will listen for requests form backup servers on
# must be in the form xxx.xxx.xxx.xxx (default: 0.0.0.0)
# BindTo=127.0.0.1
BindTo=0.0.0.0

# port agent will listen on (default: 1167)
LocalPort=1167
# Check the filename in user.allow to make sure it matches IP
IPAuthentication=0

# The logging directory
LogDir=..\log

Debug=0

```

Parameter	Default Value	Description
-----------	---------------	-------------

ConfDir	..\conf	Configuration directory path. Notice: The value for Local Port should match the Remote Port settings for the CDP Agent in the CDP Server.
BindTo	0.0.0.0	Local address the Agent will listen for requests from the Backup servers on.
LocalPort	1167	The Port the Agent will listen on.
IPAuthentication	0	Parameter that allow to check the filename in user.allow to make sure it matches IP. If set to "1," the Agent looks for a file in the server.allow directory matching the IP address of an incoming connection before doing RSA Key authentication. "0" means the Agent will only do RSA Key authentication and not check the source IP address of the connecting CDP Server. Tip: RSA Key authentication is VERY strong and is just like using SSH with RSA or DSA Key authentication (authentication without a password). For added security, you can have the Agent check that the source IP address of the connecting CDP Server attempting to authenticate is a configured IP address in the server.allow directory which contains CDP Server RSA public keys named with the source IP address of the CDP Server.
LogDir	..\log	Logging directory path.

Defining CDP Agent Local Port

Follow the instructions below to define Agent Port.



Note

To define Agent Port in Standard and Advanced Editions, use [Windows CDP Configuration Utility](#). See more in [Accessing CDP Configuration Utility and Configuring CDP Agent Port](#).

1. **Enterprise Edition:** Run the Windows CDP Agent Configuration Utility. Read more in [Launching the Windows CDP Agent Configuration Utility](#).

Standard and Advanced Editions: Run the Windows CDP Configuration Utility. Read more in [Launching the Windows CDP Agent Configuration Utility](#).

2. The main window of the Windows CDP Agent Configuration Utility will open. Make sure the "Agent Configuration" tab is selected.

3. On the "Agent Configuration" you can see Agent-related settings.


- CDP Agent Port - Define a Port to connect to the Agent if different from default value. Default Port is 1167.




Notice

The value for "CDP Agent Port" must match the CDP Agent Port settings in the CDP Server.

Standard,
Advanced
Edition




Enterprise
Edition




4. Click "Apply."


5. After making changes to the configuration file, you need to restart the Agent. Click "OK."




6. Restart the Agent by selecting Services > Restart CDP Agent.



7. Confirm your request to restart the Agent by clicking "OK."



8. Then you will see the notification that the service has been restarted.



See also:

- [Configuring CDP Agent Port \(Standard Edition\)](#)
- [Configuring CDP Server Ports](#)