

Configuring NFS Server on Linux

To use PXE Network Boot, you need a working DHCP server, TFTP server, and NFS server. (Read more in [Prerequisites for Using PXE Network Boot](#)).

NFS server is used to keep the read-only image of PXE boot file system. To install NFS server on the Linux distribution that supports yum, such as Fedora, CentOS, and RedHat, run the following command:

```
yum -y install nfs-utils
```

```
[root@fedora ~]# yum -y install nfs-utils
Loaded plugins: presto, refresh-packagekit
Fedora/metalink | 32 kB 00:00
fedora | 4.3 kB 00:00
fedora/primary_db | 10 MB 00:22
updates/metalink | 27 kB 00:00
updates | 4.7 kB 00:00
updates/primary_db | 4.8 MB 00:02
Setting up Install Process
Resolving Dependencies
--> Running transaction check
--> Package nfs-utils.i686 1:1.2.2-6.fc13 set to be updated
--> Finished Dependency Resolution

Dependencies Resolved

=====
Package Arch Version Repository Size
=====
Updating:
nfs-utils i686 1:1.2.2-6.fc13 updates 299 k

Transaction Summary
=====
Install 0 Package(s)
Upgrade 1 Package(s)

Total download size: 299 k
Downloading Packages:
Setting up and reading Presto delta metadata
updates/prestodelta | 691 kB 00:00
Processing delta metadata
█
```

Other Linux distributions have their own methods of software installation. For example, on distributions that support aptitude, such as Debian and Ubuntu, NFS server can be installed with the command

```
apt-get install nfs-kernel-server
```

```

root@ubuntu:~# apt-get install nfs-kernel-server
Reading package lists... Done
Building dependency tree
Reading state information... Done
The following extra packages will be installed:
  libgssglue1 libnfsidmap2 librpcsecgss3 nfs-common portmap
The following NEW packages will be installed:
  libgssglue1 libnfsidmap2 librpcsecgss3 nfs-common nfs-kernel-server portmap
0 upgraded, 6 newly installed, 0 to remove and 0 not upgraded.
Need to get 516kB of archives.
After this operation, 1,585kB of additional disk space will be used.
Do you want to continue [Y/n]? y
Get:1 http://archive.ubuntu.com/ubuntu/ maverick/main libgssglue1 i386 0.1-4 [22.4kB]
Get:2 http://archive.ubuntu.com/ubuntu/ maverick/main libnfsidmap2 i386 0.23-2 [29.1kB]
Get:3 http://archive.ubuntu.com/ubuntu/ maverick/main librpcsecgss3 i386 0.19-2 [33.1kB]
Get:4 http://archive.ubuntu.com/ubuntu/ maverick/main portmap i386 6.0.0-2ubuntu1 [37.5kB]
Get:5 http://archive.ubuntu.com/ubuntu/ maverick/main nfs-common i386 1:1.2.2-1ubuntu1 [232kB]
Get:6 http://archive.ubuntu.com/ubuntu/ maverick/main nfs-kernel-server i386 1:1.2.2-1ubuntu1 [162kB]
Fetched 516kB in 2s (197kB/s)
Preconfiguring packages ...
Selecting previously deselected package libgssglue1.
(Reading database ... █

```

After the installation, you will have to create NFS share. NFS share is just a directory that can be mounted from remote clients. It is recommended that NFS share directory is not used for any other purposes. Create the directory to be shared over NFS with the command

```
mkdir /nfsroot
```

After creating the directory, open the file `/etc/exports` in your favorite text editor.

This file contains a list of NFS shares, IP addresses they can be mounted from, type of access (read-only or read-write), and other sharing options. Let's assume that your IP subnet with the servers for Bare-Metal Restore is `192.168.5.0/24`. Add to `/etc/exports` the following line:

```
/nfsroot 192.168.5.0/24(ro,no_root_squash,no_subtree_check)
```

```
1 /nfsroot 192.168.5.0/24(ro,no_root_squash,no_subtree_check)█
```

Save the file and run the following command:

```
exportfs -r
```

Then you can start NFS service by executing the following command:

```
/etc/init.d/nfs start
```

To make sure your NFS share is visible to the client, run the following command on NFS server:

```
showmount -e
```

```
[root@pxeserver ~]# exportfs -r
[root@pxeserver ~]# /etc/init.d/nfs start
Starting NFS services:           [ OK ]
Starting NFS quotas:           [ OK ]
Starting NFS daemon:           [ OK ]
Starting NFS mountd:           [ OK ]
[root@pxeserver ~]# showmount -e
Export list for pxeserver:
/nfsroot 192.168.5.0/24
```

The command should return something like this:

```
Export list for pxeserver:
/nfsroot 192.168.5.0/24
```



Note

NFS service depends on the portmap service and usually will not work if portmap is not running. But this dependency is not always hardcoded into the startup script, so sometimes the script will try to start NFS service without trying to find out if portmap is already started and start it if it is not. In such case NFS will fail to start. So if for any reason NFS service fails to start, try to start portmap first by executing the command

```
/etc/init.d/portmap start
```

Now you can proceed to [Installing PXE Network Boot](#).