

Registering a Paid Standard Edition License

If Standard Edition does not have a valid license key, then a perpetual free license key that never expires is generated. On the [Dashboard](#) above the main navigation screen, the "Download Now" button is displayed.



Notes


- Free licenses never show up on or involve the license server.
- Free licenses are indicated as "Free" in the "[License Information](#)" screen.
- If you are running a trial license in 4.0.1 or an earlier version, it stays a trial (not a perpetual free license).
- If you are installing 4.2.0 on a new installation, you automatically get a perpetual free license.
- If you are running 4.0.1 or an earlier version on a paid license and upgrade, there are no changes.

You can register a paid Standard Edition license from either a trial or a free license. This hides the up-sell on the Dashboard. Follow the instructions below to register a paid Standard Edition license.


1. Click on "Configuration" in the Main Menu to open the "Configuration" window.




2. In the "Configuration" menu, click on "Accessing License Information."




3. The "License Information" window opens.



4. Click the "Upgrade License" button.




5. The "License Activation" window opens. Click "Next" to continue the process of activation.



6. The next dialog offers you the following activation options:

- Online activation - Online activation is automatic and requires the computer with R1Soft CDP installed to connect directly to <https://activation.r1soft.com:443>.
- Manual activation - Manual activation requires you to paste a coded message to a website form, download the license key file, then upload it to this CDP installation.



Select an option and click "Next."



Note


Only perpetual licenses can be manually activated.

7. The next screen will prompt you for the Product Key. Enter the Product Key you received from the R1Soft sales team in the "Product Key" text box on the "License Activation" screen. You can

enter an optional server description in the "Server Description" text box.


- Product Key - This is the 36-character product activation code and looks like xxxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxx. It is best to copy and paste this code into the form. The License ID cannot be empty for online/manual activation.
- Server Description - The server description is any text string. It is recorded with the license only for your records and to help you identify this license activation if you have multiple licenses.

Click "OK."



The image shows a "License Activation" dialog box with a key icon in the title bar. Inside, there is a section titled "Enter license details" with a key icon. It contains two text input fields: "Product Key" and "Server Description". The "Server Description" field contains the text "10.4.1.33". At the bottom of the dialog, there are three buttons: "Back", "OK", and "Cancel". The "OK" button, which has a green checkmark icon, is circled in red.

8. Then you will receive a confirmation of successful activation. Click "OK."



The image shows a "Success" dialog box with a close button in the top right corner. The text inside reads "Activation was successful!". Below the text is an "OK" button, which is circled in red.

9. Your license is now upgraded. The CDP Server redirects you to the Web Interface.