

Detaching Disk Safes

Detaching a Disk Safe will delete the Disk Safe configuration from this CDP Server. All configured tasks and historical task information will be lost, but the Disk Safe and all backed up data will remain on the disk. In other words, the Disk Safe's folder will be kept.

> **Note**
> You can detach only closed (disabled) Disk Safes.

Follow the instructions below to detach a Disk Safe in CDP.


1. Click on "Disk Safes" in the Main Menu to access the "Disk Safes" page.


Standard Edition	Enterprise Edition	Advanced Edition
		

2. Select a Disk Safe you want to detach and click "Close Selected". The state indicator will turn red.



3. After the Disc Safe is closed, it can be safely detached. Click on the "Detach" icon for this Disk Safe in the "Actions" column.


Standard, Advanced Edition	

Enterprise Edition	



> **Tip**
> To find a Disk Safe, you can use the Basic and Advanced List Filters. See Customizing the Disk Safes List.

> **Note**
> You can also detach several Disk Safes at once. See Bulk Removal below.

4. Confirm your request to detach the Disk Safe by clicking on "Detach" in the displayed confirmation window.





5. The Disk Safe will disappear from the "Disk Safes" list.

Standard, Advanced Edition	
Enterprise Edition	

Bulk Removal

Using the Bulk Removal, you can detach multiple Disk Safes at once.



1. Select several Disk Safes by checking the related checkboxes in the first column in the Disk Safes list.

Standard, Advanced Edition	
Enterprise Edition	


2. Click "Close Selected". The state indicator will turn red.



3. After the Disc Safes are closed, they can be safely detached. Click "Detach Selected" in the "Disk Safes" list toolbar.

Standard, Advanced Edition	
Enterprise Edition	

4. Confirm detaching of the selected Disk Safes by clicking on "Detach" in the displayed confirmation window.



5. The Disk Safes will disappear from the "Disk Safes" list.

You can also detach Disk Safes using the "Disk Safes" tab of the Agent "Details" Pane. This screen provides the same functionality as the main "Disk Safes" screen. See more information in Accessing Agents.