Setting CDP Server Users

Linux Installations | Windows Installations

Linux Installations

You can define a username and password for the CDP Server Web Interface before you can begin using the CDP Standard Edition.

```
#r1soft-setup --user DESIRED_USERNAME --pass DESIRED_PASSWORD
```

After running you will see output similar to:

r1soft-setup --user admin --pass r1soft Server username and password set The R1Soft CDP Server must be restarted for these changes to take effect Use '/etc/init.d/cdp-server restart' to restart.

Then restart the CDP server. See Restarting CDP Server.

Windows Installations

Using the "Reset User" function you can:

- Change the password of the existing CDP Server user without entering the old password.
- Create a new user account for Windows CDP Server.

Follow the instructions below to use the "Reset User" function in Windows CDP Configuration Utility.

1. Run the Windows CDP Configuration Utility by going to Start > (All) Programs > R1Soft CDP Backup > CDP Configuration Utility.



2. Select the "Credentials" tab. This tab is shown by default.

Standard Edition	CDP Configuration Utility File Services Help Credentials Server Configuration Agent Configuration Set Heap Size	
Enterprise Edition	CDP Configuration Utility File Services Help Credentials Server Configuration Set Heap Size	

- 3. Fill in the following fields:
 - Username Enter login name of the existing user to reset the password. Enter a new login name to create a new user.
 - Password Enter a password for the user account.
 - Verify Repeat the password.

🦁 CDF	P Configura	tion Utility								. 🗆 🗙
File	Services	Help								
Creder	ntials Serve	r Configuration	Agent Config	guration						
Rese	ts a CDP use	er. Complete th	e fields and clic ser	k Apply to sav	ve the chang changes to ta	es. Once don ike effect.	ie, you will	have to rest	art the CDP S	Server
				Jsemame: Password: Venily:		_				
						Ap	ply		Cancel]

4. Click the "Apply" button to save the changes.

	Apply	Cancel

5. Once the user is reset successfully, you will see the confirmation message. Click "OK."



6. Now you must restart the CDP Server service for your changes to take effect. See Restarting CDP Server.

See also:

- Configuring User Options (Standard Edition)
- Adding Users (Enterprise Edition)
- Editing User Properties (Enterprise Edition)