

Uninstalling Standard Edition on Linux

To remove R1Soft CDP Server Standard Edition from your computer, follow the below steps.



Notice

RPM (RHE/CentOS/Fedora/Suse/Mandriva) and APT (Debian/Ubuntu) Linux distributions have different uninstallation processes.

RPM/YUM-based Installations | DEB/APT-based Installations

RPM/YUM-based Installations

1. Type the removal command and press <Enter>.

```
rpm -e r1soft-cdp-server r1soft-setup r1soft-cdp-standard-edition r1soft-cdp-agent
```

```
[root@centos-server ~]# rpm -e r1soft-cdp-server r1soft-setup r1soft-cdp-standard-edition r1soft-cdp-agent
/etc/init.d/cdp-server : cdpserver (no pid file) not running
error reading information on service cdp-server: No such file or directory
R1Soft uninstall has kept /usr/sbin/r1soft and relevant configuration information.
To complete the uninstall, this directory must be removed manually
/etc/init.d/cdp-agent stop: cdp stopped
```

2. The uninstall program stops CDP Server. It displays information about file removals and may list files that must be removed manually.
3. Once the uninstallation process is complete, R1Soft CDP Server Standard Edition is removed from your computer.

DEB/APT-based Installations

1. Type the removal command and press <Enter>.

```
apt-get remove r1soft-cdp-server r1soft-setup
```

```
root@debian-server:~# apt-get remove r1soft-cdp-server r1soft-setup
Reading package lists... Done
Building dependency tree
Reading state information... Done
The following packages will be REMOVED:
 r1soft-cdp-agent r1soft-cdp-async-agent-2-6 r1soft-cdp-server r1soft-cdp-standard-edition r1soft-setup
0 upgraded, 0 newly installed, 5 to remove and 51 not upgraded.
After this operation, 0 B of additional disk space will be used.
```

2. You will be asked to confirm the uninstallation. Type "Y" and press <Enter> to confirm.

**Tip**

"Yes" is the default answer. To select it, press <Enter>.

```
Do you want to continue [Y/n]? y
(Reading database ... 26614 files and directories currently installed.)
Removing r1soft-cdp-standard-edition ...
Removing r1soft-cdp-server ...
/etc/init.d/cdp-server : cdpserver (no pid file) not running
R1Soft uninstall has kept /usr/sbin/r1soft and relevant configuration information.
To complete the uninstall, this directory must be removed manually
Removing r1soft-cdp-async-agent-2-6 ...
Removing r1soft-cdp-agent ...
/etc/init.d/cdp-agent stop: cdp stopped
Removing r1soft-setup ...
Processing triggers for man-db ...
```

3. The uninstall program stops CDP Server. It displays information about file removals and may list files that must be removed manually.
4. Once the uninstallation process is complete, R1Soft CDP Server Standard Edition is removed from your computer.